

Automatic role definitions - Import of data from CSV

This LRT can be used to import automatic roles which are assigned based on an EAV attribute of a contract.

Prepare CSV file

Here is an example of CSV file which can be used for import role definitions.

```
roles;position;organizational unit  
Manager;Leader;Business  
"MASTER RO  
PAY-OP  
PAY-SP  
PAY-BLL  
AMT-BLK  
ACC-CLOSE";Manager;Business
```

As you can see roles column can be single or multivalued. For multivalued roles, definition from the same row will be added to every role. CSV file can have optional number of columns, role and automatic role definitions columns are specified in setup of LRT.

Create new LongRunningTask

Now we will create the new LongRunningTask(LRT). As shown in the picture, go to Settings → Task scheduler → Scheduled tasks and hit green "Add" button to add new LRT.

Fill all attributes

Now we need to create new LRT with these attributes:

- Task type - **ImportAutomaticRoleAttributesFromCSVExecUTOR** - Import csv file - dropzone to select or drop csv file
- Column with roles - Name of the column with roles in csv file
- Column with description - name of the column with role description, can be also used to update description
- Column separator - separator of columns in csv file
- Multi value separator - (Char, default: new line) separator of multi valued role names in csv file, new line separator is default export from excel, but for better clarity of csv file, it's recommended to use some symbol instead
- Column with first attribute in csv file
- First contract eav name - name of existing eav attribute of contract which will be checked for match with automatic attribute
- Column with second attribute in csv file
- Second contract eav name - name of existing eav attribute of contract which will be checked for match with automatic attribute

Parametry úlohy

Import csv file

Přetáhněte soubory na tuto plochu a nebo na ní klikněte pro výběr souborů. *

Column with roles

roles *

Column separator

;

Multi value separator

default is new line

Column with first attribute

Position *

First contract eav code

Position *

Column with second attribute

Organizational Unit

Second contract eav code


Organizational_Unit

Zavřít


Uložit

Run the task

Now we just need to hit run.



And we also need to process it in all tasks.



You can check status about created role definitions in "all tasks" panel in task detail. Here you can find information about created or already existing automatic role definitions.

Everything should be set up so far and when the task ends, existed roles has got automatic role definitions on specified attributes.

Number of processed items means how many role names is in csv. Number of finished items are roles that were found in IdM and has't got automatic role definition.

Known issues

If you delete or upload new file via dropzone, you should delete old files, created from previous uploads.

From:
<https://wiki.czechidm.com/> - CzechIdM Identity Manager

Permanent link:
https://wiki.czechidm.com/tutorial/adm/automatic_role_definitions_-_import_of_data_from_csv?rev=1573133477

Last update: 2019/11/07 13:31

